



Quick Start Guide – Installation

The only operating systems tested and that showed consistent results are Windows 2000 and XP. If you are using Windows 98 or ME, all updates issued from Microsoft concerning these operating systems must be installed. Pacelogic will not take responsibility operating systems other than Win2000 and XP.

1. Download PACESETTER I and save in zip format in a new directory titled PACESETTERI in your PROGRAM FILES folder.
2. Run Setup
3. If you get any error messages that say your system files are out of date, you must update these files before continuing. Or upgrade to Windows 2000 or XP.
4. Login with Admin, Admin
5. Add users to your system by selecting Maintain. The User tab will be active. Enter User Id, Password, and Level. 1 = highest level and used for managers.
6. Top Tool bar, select Tools > Preferences
7. The General tab will reveal default options for Locations. Accept these defaults if the location file supplied is not altered.

The supplied Locations assume a shelf that is 3 levels high and 5 bins wide. The highest level (3) is for bulk storage. It assumes that these shelves are aligned parallel to each other forming 6 aisles. Entering the aisle from the lowest bin number, these aisles are viewed Left and Right. PACEMAIN001L01OPEN is a miscellaneous location

Key = 18 PA CE MAIN 001L 01 0001
Site -2, Bldg - 2, Sect - 4, Aisle - 4(l-r), Level - 2, Bin- 4
Type P = picking/primary B =
Bulk
UM Desc.
Picking seq.
Minimum qty to trigger replenishment

8. Customer defaults assume that customers will accept partial shipments. Priority levels are 1 – 9, with 1 being the best. 8 is next to lowest priority and generally assigned. Default status table, user defined, is a general table used for customer orders and receiving. OK will allow the customer orders to be imported and processed with additional attention and is the standard default.
9. Ignore Serial Number (SN) and Lot control (LOT) also Batch Picking.

The screenshot shows the 'Preferences' dialog box with the 'General Settings' tab selected. The dialog has a blue title bar with standard window controls. Below the title bar are four tabs: 'General Settings', 'Customer Defaults', 'SN & LOT Tracking', and 'Batch Picking'. The main area contains four dropdown menus for location and unit of measure settings, and two groups of checkboxes for order and inventory options. At the bottom are 'OK', 'Apply', and 'Cancel' buttons.

Default Receiving Location : PACEMAIN000L00DOCK

Default New Item Pick Location : PACEMAIN000L00OPEN

Default New Item Bulk Location : PACEMAIN002L030001

Default Re-Order Unit Of Measure : EACH

Customer Orders Options:
 Pending Orders Only

Physical Inventory Options:
 Use Blind Inventory

OK Apply Cancel

The screenshot shows the 'Preferences' dialog box with the 'Customer Defaults' tab selected. The dialog has a blue title bar with standard window controls. Below the title bar are four tabs: 'Global Settings', 'Customer Defaults', 'SN & LOT Tracking', and 'Batch Picking'. The main area contains three dropdown menus for picking, priority, and status settings. At the bottom are 'OK', 'Apply', and 'Cancel' buttons.

Default Value For Partial Picking : True

Default Value For Priority : 8

Default Value For Status : Okay

OK Apply Cancel